


Downloading and Installing OpenCV


URL: https://opencv.org/releases/




1. Extract the file











2. Configure the environment variable









编辑环境变量 \times C:\Program Files (x86)\Common Files\Oracle\Java\javapath 新建(N) C:\Program Files (x86)\Intel\iCLS Client\ C:\Program Files\Intel\iCLS Client\ 编辑(E) %SystemRoot%\system32 %SystemRoot% 浏览(B)... %SystemRoot%\System32\Wbem %SYSTEMROOT%\System32\WindowsPowerShell\v1.0\ 删除(D) C:\Program Files (x86)\Intel\Intel(R) Management Engine Comp... C:\Program Files\Intel\Intel(R) Management Engine Component... C:\Program Files (x86)\Intel\Intel(R) Management Engine Comp... 上移(U) C:\Program Files\Intel\Intel(R) Management Engine Component... %SYSTEMROOT%\System32\OpenSSH\ 下移(O) C:\Program Files\Intel\WiFi\bin\ C:\Program Files\Common Files\Intel\WirelessCommon\ %JAVA HOME%\bin 编辑文本(工)... C:\Program Files\MATLAB\R2016a\runtime\win64 C:\Program Files\MATLAB\R2016a\bin C:\Program Files\MATLAB\R2016a\polyspace\bin C:\cygwin64\bin


Click "New" button

确定

取消










3. Configure files in VS 2019


(1) Create an empty project in vs2019






Right click the mouse at your project name and choose "Properties" menu item







copy the directory

Copy the "opencv2" folder which is in the "D:\Software\opencv\build\include" to the directory you just copied




Open the "Properties" window for the second time, and choose "Library Directories"






copy the directory


Copy the two files (opencv_world440.lib and opencv_world440d.lib) which are in the "D:\Software\opencv\build\x64\vc15\lib" to the directory you just copied




Open the "Properties" window for the third time, and choose "Linker"




Copy the filename "opencv_world440d.lib" in the D:\Software\opencv\build\x64\vc15\lib folder to the "Additional Dependencies"






Test your opency


Notice: Debug must be x64





Note:

After OpenCV is installed, you will need to add additional dependencies to the **project** each time you use it. Copy the file name of OpenCV_World440d.lib into the additional dependency. Otherwise, the compiler will report a LINK 2019 error, and many OpenCV library functions cannot be resolved.



Install openCV on macOs

https://blog.csdn.net/wo164683812/article/details/80114999

https://www.cnblogs.com/linjk/p/6029306.html

Configure openCV on CLion

https://www.pianshen.com/article/539860361/

Install openCV on ubantu

https://learnopencv.com/install-opencv-3-4-4-on-ubuntu-16-04/